



Adding Dispatch Categories

1. In the M&U module, navigate to the **Master Data / Dispatch Category** menu.
2. Leave both fields blank and select the **Add** button.

The **Dispatch Ctgr Id** is maintained at the Maintenance Activity level (e.g., **Dispatch Ctgr Id** cannot be duplicated within a Maintenance Activity). Sub Categories cannot be duplicated within the Dispatch Category.

Dispatch Categories are used to further define Equipment Pool groupings. They define both Categories and Sub Categories.

Search Criteria	
Dispatch Ctgr Id	<input type="text"/>
Dispatch Ctgr Desc	<input type="text"/>
<input type="button" value="Add"/>	<input type="button" value="Search"/> <input type="button" value="Reset"/>

3. On the **Add** page, enter a **Dispatch Ctgr Id** and **Dispatch Ctgr Desc**. The **Dispatch Ctgr Long Desc** is optional.
4. In the **Sub Ctgr** table, enter a **Sub Ctgr Id** and **Sub Ctgr Desc**.
5. If more than one Sub Category is needed, select the **New Row** button and repeat Step 4.
6. To remove an unwanted **Sub Ctgr**, select the *Delete* hyperlink. (This option works in both the Add and Update processes.)
7. Once all Sub Categories have been entered, select the **Add** button to complete the process.

Add			
*Dispatch Ctgr Id	<input type="text" value="UTILITY"/>	*Dispatch Ctgr Desc	<input type="text" value="TRUCK, UTILITY"/>
Dispatch Ctgr Long Desc	<input type="text" value="TRUCK, UTILITY"/>		
History Remarks	<input type="text"/>		

Sub Ctgr		
Delete	*Sub Ctgr Id	*Sub Ctgr Desc
Delete	<input type="text" value="CARGO"/>	<input type="text" value="TRUCK, UTILITY, CARGO"/>
Delete	<input type="text" value="DUMP"/>	<input type="text" value="TRUCK, UTILITY, DUMP"/>
Delete	<input type="text" value="PLATFORM"/>	<input type="text" value="TRUCK, UTILITY, PLATFORM"/>
Delete	<input type="text" value="TANK"/>	<input type="text" value="TRUCK, UTILITY, TANK"/>
<input type="button" value="New Row"/>		

A **Dispatch Ctgr Id** must have at least one **Sub Ctgr Id**. There is a maximum of 50 Sub Ctgr per Dispatch Ctgr.





Updating/Deleting Dispatch Categories

1. In the M&U module, navigate to the **Master Data / Dispatch Category** menu.
2. Enter any search criteria available or leave both fields blank to return all available Dispatch Categories. *Note:* You can use the % (wildcard) search on both fields.
3. Select the **Search** button.
4. The **Search Results** page displays. Select the *Update* hyperlink to revise a Dispatch Category, or the *Delete* hyperlink to remove an Dispatch Category.
5. If Updating: Enter your changes and select the **Update** button.
6. If Deleting: Verify Address data to delete and select the **Delete** button.

A **Dispatch Ctgr Id** cannot be deleted if it is associated with a maintenance asset record. If you select the **Delete** hyperlink for this type of **Dispatch Ctgr Id**, an error will display.

Search Criteria		Dispatch Ctgr Id	Dispatch Ctgr Desc
Search Results			
Update	Delete	Dispatch Ctgr Id	Dispatch Ctgr Desc
Update	Delete	SEDAN	AUTOMOBILE, SEDAN
Update	Delete	SMALL	BOAT, SMALL
Update	Delete	UTILITY	TRUCK, UTILITY
<input type="button" value="Add"/> <input type="button" value="Cancel"/>			

